



CAN Frames for controlling the iWheel

CAN configuration

CAN Bus speed: **1MBps**

Sample point: **62.5%** of a bit time.

Setpoints write commands

	CAN Frame ID (dec)	Data							
		B0	B1	B2	B3	B4	B5	B6	B7
LEFT		Left Motor Setpoint Type (0: Free, 1: Speed, 2: Current)	Left Speed Setpoint MSB (int16s, mm/s)	Left Speed Setpoint LSB (int16s, mm/s)	Left Current Setpoint MSB (int16s, mA)	Left Current Setpoint LSB (int16s, mA)			
	266								
RIGHT		Right Motor Setpoint Type (0: Free, 1: Speed, 2: Current)	Right Speed Setpoint MSB (int16s, mm/s)	Right Speed Setpoint LSB (int16s, mm/s)	Right Current Setpoint MSB (int16s, mA)	Right Current Setpoint LSB (int16s, mA)			
	298								

Important notes

- Setpoint frames (write commands) must be sent periodically at a frequency higher than 1 frame/second. There is a 1 second timeout that make the motor stops if no more frames are sent.
- Range for current Setpoint is $\pm 2000\text{mA}$

Max Strom 2A

Was ist max Speed?

Variables read commands


* RPM

	CAN Frame ID (dec)	Data							
		B0	B1	B2	B3	B4	B5	B6	B7
LEFT	256	Speed MSB (int16s, RPM)	Speed LSB (int16s, RPM)						
	257	Battery Voltage (int8u, dV)	Controller Temperature (int8u, °C)	Odometry Ticks MSB (int32s)	Odometry Ticks (int32s)	Odometry Ticks (int32s)	Odometry Ticks LSB (int32s)	CPU Usage (int8u, %)	
RIGHT	288	Speed MSB (int16s, RPM)	Speed LSB (int16s, RPM)						
	289	Battery Voltage (int8u, dV)	Controller Temperature (int8u, °C)	Odometry Ticks MSB (int32s)	Odometry Ticks (int32s)	Odometry Ticks (int32s)	Odometry Ticks LSB (int32s)	CPU Usage (int8u, %)	
	290	Estimated Pose X (int16s, mm)	Estimated Pose X (int16s, mm)	Estimated Pose Y (int16s, mm)	Estimated Pose Y (int16s, mm)	Estimated Pose Z (int16s, mm)	Estimated Pose Z (int16s, mm)	Estimated Pose PSI (int16s, mrad)	Estimated Pose PSI (int16s, mrad)

Important notes

- Odometry: 60 ticks/rotor revolution
- Variables are send out without request periodically (40ms period for: 257,289,290 and 4ms period for: 256,288)

First trials with the iWheel attached to a table



On the pictures above you can see the iWheel component without tire-

We have assembled the shaft of the iWheel to a fork to facilitate you to attach this set to your table by using a clamp.

Important:

You will receive 2 iWheels, the once assembled to the fork will be programmed as a "Right iWheel", the other one will be programmed as a "Left iWheel"



Allocating the rotor in the middle



Pouring the orange colored polyurethane resin

iWheel with cover

